


---

How to Install

# AutoNAICS

Version 2.1.7



# Contents

- Installing and Uninstalling AutoNAICS ..... 1**
  - What You Need ..... 1
  - Installing a New Copy of AutoNAICS on Your PC ..... 2
  - Preparing a PC to Run AutoNAICS from a Server ..... 2
  - Upgrading or Reinstalling AutoNAICS ..... 3
  - Uninstalling AutoNAICS ..... 3
  
- Guidelines for Network Administrators..... 4**

# Installing and Uninstalling AutoNAICS

---

## What You Need

To use AutoNAICS, you need the following:

- Microsoft Windows 95/98 or NT Workstations (32-bit),
- 100 MHz Pentium (200 MHz recommended),
- 16MB RAM (32MB recommended), and
- 22MB disk space.

The AutoNAICS CD contains a setup utility that installs AutoNAICS and the Code Conversion Tool. How you install AutoNAICS depends on whether you are installing for the first time, accessing the software through a server, or upgrading from a previous version.


- New AutoNAICS users who wish to install AutoNAICS on their PCs should refer to "Installing a New Copy of AutoNAICS on Your PC" on page 2.
- AutoNAICS users who run AutoNAICS from a server should refer to "Preparing a PC to Run AutoNAICS from a Server" on page 2.
- If you are upgrading or reinstalling a new version of AutoNAICS, refer to "Upgrading or Reinstalling AutoNAICS" on page 3.

---

## Installing a New Copy of AutoNAICS on Your PC

Follow these instructions if you are installing a copy of AutoNAICS on a personal computer that does not contain an earlier version of AutoNAICS.

### **To install AutoNAICS:**

1. Close any applications that you have running.
2. Double click **AutoNAICSPCv2.1.7.exe**.
3. The WinZip Self Extractor - AutoNAICSInstall.exe dialog box appears. Click **Setup**.
4. Type the password in the Password dialog box. Click **OK**.
5. An AutoNAICS Setup dialog box appears. If, as directed in Step 1, you closed all open applications, click **OK**. If not, click **Exit Setup** and begin the installation process again.
6. A second AutoNAICS Setup dialog box appears. If you wish to install to the suggested directory, click . The program will install AutoNAICS into c:\Program Files\NAICS. **Note:** You may change the program directory if desired by clicking **Change Directory** and designating a directory of your choice.
7. If you wish to use the suggested **BLS** program group, click **Continue**. Otherwise, type a new name in the program group input line and click **Continue**.
8. Click **Ok** when installation is complete.

---

## Preparing a PC to Run AutoNAICS from a Server

[**Network Administrators:** Please follow "Instructions for Network Administrators" on page 4.]

When AutoNAICS is available on a network, users can save disk space by running a shared version of AutoNAICS from the network.

### **To install AutoNAICS from a server:**

Run **setup.exe**, located in the directory designated by the network administrator. The setup program:

- Installs the necessary files to the computer, and
- Creates the **BLS** program group.

---

## Upgrading or Reinstalling AutoNAICS

Before upgrading or reinstalling AutoNAICS, uninstall previous versions of the software. "Uninstalling AutoNAICS" is described on page 3. After old copies are removed, either:

1. Install AutoNAICS on your PC using the procedures described in "Installing a New Copy of AutoNAICS on Your PC" on page 2,  
**or**
2. Prepare a PC to use the server version of AutoNAICS described in "Preparing a PC to Run AutoNAICS from a Server" on page 2.

**Note:** If you created Shared Notes or Personal Notes during previous AutoNAICS operation, their resulting files are *not* deleted when upgrading, reinstalling, or uninstalling AutoNAICS.

---

## Uninstalling AutoNAICS

Uninstall AutoNAICS using the Windows **Add/Remove Programs** utility.

### ***To uninstall AutoNAICS:***

1. Click the Windows **Start** button, select **Settings**, and then click **Control Panel**.
2. Double click **Add/Remove Programs**.
3. On the **Install/Uninstall** tab, select **AutoNAICS** from the list of installed programs.
4. Click the **Add/Remove...** button and follow the instructions on the screen.

**Note:** If you created Shared Notes or Personal Notes during previous AutoNAICS operation, their resulting files are *not* deleted when upgrading, reinstalling, or uninstalling AutoNAICS.

# Guidelines for Network Administrators

---

## Instructions for Network Administrators

### *Network Setup Instructions:*

- 1. Create a network directory.**  
Create a network directory that is accessible to all users of the AutoNAICS system. Users will need full access (read/write/modify) to this directory.
- 2. Copy *AutoNAICSNetv2.1.7.exe* into the new directory.**  
Place a copy of *AutoNAICS2NetInstall.exe* into the directory you created.
- 3. Run *AutoNAICSNetv2.1.7.exe*.**  
*AutoNAICSNetv2.1.7.exe* is a self-extracting zip file that will extract all the AutoNAICS files to the current directory.
- 4. Configure the setup file.**  
Edit *setup.lst* using Notepad. *Setup.lst* is an old-fashioned ini file. Change the AutoNAICS Key in the NetPath section to point to the location of *AutoNAICS.exe* on the network. This *must* be the path the users will use to access the program. **Note:** It is very important this be correct. The setup program uses this information when individuals install.  
  
[NetPath]  
  
AutoNAICS="\\server\_name\the\_directory\AutoNAICS.exe"
- 5. Install clients.**  
Have users run *setup.exe*, located in the directory into which you extracted the files. The setup program will install the necessary files to a user's computer and create a BLS program group.